



## Compatibility

### Adagio

BankRec 8.1A – 9.2A  
Console 9.1A, 9.2B  
DataCare 8.1A - 9.2A  
DocStore 9.3A  
ePrint 9.0A, 9.2A  
FX 8.1A – 9.2A  
GridView 9.3A  
Inventory 8.1A – 9.2A  
Invoices 8.1A – 9.2A  
JobCost 8.1A – 9.2A  
Lanpak 9.3A  
Ledger 8.1A – 9.3A  
MultiCurrency 8.1A – 9.2B  
OrderEntry 8.1A – 9.3A  
Payables 8.1A – 9.3A  
PurchaseOrders 8.1C – 9.3A  
Receivables 8.1A – 9.2A  
SalesAnalysis 8.1A – 9.2A  
SalesCQ 8.1A – 9.2B  
Time&Billing 8.1A – 9.2A

### Other

Any product for which an Adagio  
Data Dictionary has been  
created  
Excel Workbooks  
Island Microsystems products  
DSN / UDL data sources  
MS Office 2007, 2010, 2013  
2016, 365  
MS Windows 7, 8, 8.1, 10  
Any product that uses the  
Adagio Data Source (ADS)

### Note

The most up-to-date  
compatibility information is on  
the Product Compatibility Info  
link at [www.softrak.com](http://www.softrak.com).

## Enhancements

- Compatible with GridView 9.3A.
- Compatible with Adagio DocStore.
- To help prevent accidental deletion of records, the “Delete records” menu choices are only displayed when “/DELETE” is on the command line.
- When “Delete all” is chosen, confirmation must be provided before all the records are deleted.

## Enhancements and revisions in earlier versions

Refer to the Readme help file for details of enhancements and revisions in earlier versions or Change Log under [Documentation](#) for this module on Softrak's web site.

## Installing

Adagio GridView-RW is an Add-on product for Adagio GridView. **Adagio GridView 9.3A must be installed before installing the GridView-RW Add-on. Adagio GridView-RW and Adagio GridView must be at the same version.** If the version of GridView-RW does not match the version of GridView the GridView-RW functions are disabled and GridView will operate in Read-Only mode.

Not For Resale (NFR) versions of Adagio GridView-RW are not available.

Note: When the GridView-RW add-on is active (i.e. GridView is started with the /RW parameter on the command line) the F2 key edits a field rather than opening Edit | Defaults. To open Edit | Defaults with a hot key use Shift F2 instead. When the add-on is not active F2 will open Edit | Defaults.

To install Adagio GridView-RW, you need the serial number and install code from the download email sent to you by Softrak Systems.

If you are installing an upgrade, you need the serial number and install code from the upgrade download instruction email. A previous version of Adagio GridView-RW should already be installed on your computer before installing the upgrade. If a previous version is not already installed, you can still install the upgrade. After entering the upgrade serial number and install code, you will also have to enter the serial number and install code from your previous version.

**Read the 'Upgrading' sections below before installing an upgrade.**

To install Adagio GridView-RW, an upgrade, or Service Pack, run the program file you downloaded. Once the install program is running, you can click the View button for detailed installation instructions in the Readme help.

## Upgrading

### Upgrading to this Version

### Upgrade Complexity:

Easy ●

**You may need to reset the toolbar to show new buttons added in GridView 9.3A.**

Select View | Customize from the menu, then select each of the Toolbar's options and click the Reset button.

**Note:** When the GridView-RW add-on is active (i.e. GridView is started with the /RW parameter on the command line), the ChartView functions in GridView are not available.

**Note:** When upgrading other Adagio modules, if a new data dictionary is installed by the module, the GridView views originally created for earlier versions of the module should be adjusted to use the new dictionary. See the Release Notes for the modules to determine if there is a new dictionary. If there is a new dictionary, **Views used with GridView-RW MUST be updated to use the new dictionary to avoid the possibility of data corruption.** GridView has the ability to convert existing views when the dictionary changes with the release of an upgrade version of an Adagio module.

