

Release Notes

The most up-to-date compatibility information is on the [Product Compatibility Info](#) link at www.softrak.com.



Adagio®

BankRec 8.0A – 8.1D
Checks 8.0A – 8.1B
Contacts 8.0A
DataCare 8.1A – 9.0A
FX 8.0A – 9.0B
GridView 9.1A (required)
Inventory 8.0A – 8.1D
Invoices 8.0A – 9.0B
JobCost 8.1A, 8.1C
Ledger 8.0A – 9.0D
MultiCurrency 8.0A – 8.1B
OrderEntry 8.0A – 8.1E

Payables 8.0A – 8.1E
Purchase Orders for Adagio 8.1A, 8.1B
PurchaseOrders 8.1C
Receivables 8.0A – 9.0C
SalesAnalysis 8.0A – 9.0B
SalesCQ 8.1A - 8.1C
Time&Billing 8.0A – 8.1C

Other

Any product for which an Adagio Data Dictionary has been created
MS Office 2003, 2007, 2010
MS Windows XP, Vista, 7, 8

Enhancements and revisions in Adagio ChartView (2013.06.01)

- ◆ Initial Release of Adagio ChartView. Requires GridView 9.1A.

Installing

Adagio ChartView is an Add-on product for Adagio GridView. **Adagio GridView 9.1A must be installed before installing the ChartView Add-on. Adagio ChartView and Adagio GridView must be at the same version.** If the version of ChartView does not match the version of GridView the ChartView functions are disabled in GridView.

ChartView does not use Adagio Lanpak licenses.

A Not For Resale (NFR) version of Adagio ChartView is not available and is not needed. The NFR version of GridView provides full ChartView functionality. An Evaluation version of Adagio ChartView is not available. If ChartView is not installed, GridView includes the ChartView functionality but charts will only display for 10 seconds.

To install Adagio ChartView you need the serial number and install code from the download email sent to you by Softrak Systems.

To install Adagio ChartView, run the program file you downloaded. Once the install program is running, you can click the View button for detailed instructions in the Readme help.

If Adagio ChartView is installed on a network you do **not** need to do a workstation install on other stations. However, a workstation install is required for GridView itself.

You need to reset the toolbar to show the new ChartView button in GridView. Select View | Customize from the menu, then select each of the Toolbars listed and click the Reset button.

Note: When the GridViewRW add-on is active (i.e. GridView is started with the /RW parameter on the command line), the ChartView functions in GridView are not available.

-- end --