

## Release Notes

The most up-to-date compatibility information is on the **Product Compatibility Info** link at [www.softtrak.com](http://www.softtrak.com).

**Adagio®**

BankRec 8.0A – 8.1D  
Checks 8.0A – 8.1B  
Contacts 8.0A  
DataCare 8.1A - 9.0A  
FX 8.0A – 9.0B  
GridView 9.1A (required)  
Inventory 8.0A – 8.1D  
Invoices 8.0A – 9.0B  
JobCost 8.1A, 8.1C  
Lanpak 9.0E  
Ledger 8.0A – 9.0D  
MultiCurrency 8.0A – 8.1B  
OrderEntry 8.0A – 8.1E

Payables 8.0A – 8.1D  
Purchase Orders 8.1C  
Purchase Orders for Adagio 8.1A, 8.1B  
Receivables 8.0A – 9.0C  
SalesAnalysis 8.0A – 9.0B  
SalesCQ 8.1A - 8.1C  
Time&Billing 8.0A – 8.1C

**Other**

Any product for which an Adagio Data Dictionary has been created  
MS Office 2003, 2007, 2010  
MS Windows XP, Vista, 7, 8

### Enhancements and revisions in Adagio GridView-RW 9.1A (2013.04.03)

- ◆ Compatible with Adagio GridView 9.1A. Requires GridView 9.1A.
- ◆ The 'Auto-refresh' option on views is ignored when GridView is opened in RW mode so that changes you have made will not be lost if you have not saved yet and the view refreshes.

### Enhancements and revisions in earlier versions of Adagio GridView-RW

- ◆ Refer to the Readme help file for details of enhancements and revisions in earlier versions or [Historical Enhancements](#) under Products on Softtrak's web site.

### Installing

Adagio GridView-RW is an Add-on product for Adagio GridView. **Adagio GridView 9.1A must be installed before installing the GridView-RW Add-on. Adagio GridView-RW and Adagio GridView must be at the same version.** If the version of GridView-RW does not match the version of GridView the GridView-RW functions are disabled and GridView will operate in Read-Only mode.

Evaluation and Not For Resale (NFR) versions of Adagio GridView-RW are not available.

To install Adagio GridView-RW you need the serial number and install code from the download email sent to you by Softtrak Systems.

If you are installing an upgrade, you need the serial number and install code from the download instructions email. A previous version of Adagio GridView-RW should already be installed on your computer before installing the upgrade. If a previous version is not already installed, you can still install the upgrade. After entering the upgrade serial number and install code, you will also have to enter the serial number and install code from a previous version.

To install Adagio GridView-RW (or an upgrade), run the program file you downloaded. Once the install program is running you can click the View button for detailed instructions in the Readme help.

If Adagio GridView-RW is installed on a network you do **not** need to do a workstation install on other stations. However, a workstation install is required for GridView itself.

Note: When the GridView-RW add-on is active (i.e. GridView is started with the /RW parameter on the command line) the F2 key edits a field rather than opening Edit | Defaults. To open Edit | Defaults with a hot key use Shift F2 instead. When the add-on is not active F2 will open Edit | Defaults.

Note: You must refresh an existing view before you can edit fields. The F2 key and double clicking in a cell are not active until you refresh.

### Upgrading to this Version

Upgrade Complexity: **Easy** ●

There are no considerations or actions required when upgrading from GridView-RW 9.0F.

Note: When upgrading other Adagio modules, if a new data dictionary is installed by the module, the GridView views originally created for earlier versions of the module should be adjusted to use the new dictionary. See the Release Notes for the modules to determine if a there is a new dictionary. If there is a new dictionary, **Views used with GridView-RW MUST be updated to use the new dictionary to avoid the possibility of data corruption.** GridView has the ability to convert existing views when the dictionary changes with the release of an upgrade version of an Adagio module.

## Upgrading to this Version from earlier versions

Upgrade Complexity:

Easy ●

GridView-RW 9.1A has a new program icon. The icon for GridView-RW is available in GridView.EXE and can be applied to your shortcut that contains the /rw parameter. To see the new icon you will need to edit the properties of any existing GridView shortcuts, click the Change Icon button and select the new image.

-- end --