



Compatibility

Adagio

BankRec 8.1E – 9.2A
Console 9.1A, 9.2B
DataCare 8.1A - 9.3A
DocStore 9.3A
ePrint 9.0A, 9.2A
FX 9.1B – 9.3A
GridView 9.3B
Inventory 8.1E – 9.2A
Invoices 9.1A – 9.3A
JobCost 8.1D – 9.2A
Lanpak 9.3A
Ledger 9.1A – 9.3A
MultiCurrency 9.2B
OrderEntry 8.1E – 9.3A
Payables 8.1E – 9.3A
PurchaseOrders 8.1C – 9.3A
Receivables 9.1A – 9.3A
SalesAnalysis 9.0B – 9.2A
SalesCQ 8.1C – 9.2B
Time&Billing 8.1D – 9.2A

Other

Any product for which an Adagio
Data Dictionary has been
created
Excel Workbooks
Island Microsystems products
DSN / UDL data sources
MS Office 2007, 2010, 2013
2016, 365
MS Windows 7, 8, 8.1, 10
Any product that uses the
Adagio Data Source (ADS)

Note

The most up-to-date
compatibility information is on
the Product Compatibility Info
link at www.softrak.com.

Enhancements

- Compatible with GridView 9.3B.
- When copying to a selected range and the source range is a single cell, the single cell value is repeated in the target range.
- Added keyboard shortcut Ctrl+Alt+U to invoke the 'Update Database & Refresh' from right-click popup context menu at the top left of a view.
- GridView-RW is available as a "Not For Resale" version for use by Adagio Reseller Partners only.

Enhancements and revisions in earlier versions

Refer to the Readme help file for details of enhancements and revisions in earlier versions or Change Log under [Documentation](#) for this module on Softrak's web site.

Installing

Adagio GridView-RW is an Add-on product for Adagio GridView. **Adagio GridView must be installed before installing the GridView-RW Add-on. Adagio GridView-RW and Adagio GridView must be at the same version.** If the version of GridView-RW does not match the version of GridView the GridView-RW functions are disabled and GridView will operate in Read-Only mode.

Note: When the GridView-RW add-on is active (i.e. GridView is started with the /RW parameter on the command line) the F2 key edits a field rather than opening Edit | Defaults. To open Edit | Defaults with a hot key use Shift F2 instead. When the add-on is not active F2 will open Edit | Defaults.

To install Adagio GridView-RW, you need the serial number and install code from the download email sent to you by Softrak Systems.

If you are installing an upgrade, you need the serial number and install code from the upgrade download instruction email. A previous version of Adagio GridView-RW should already be installed on your computer before installing the upgrade. If a previous version is not already installed, you can still install the upgrade. After entering the upgrade serial number and install code, you will also have to enter the serial number and install code from your previous version.

Read the 'Upgrading' sections below before installing an upgrade.

To install Adagio GridView-RW, an upgrade, or Service Pack, run the program file you downloaded. Once the install program is running, you can click the View button for detailed installation instructions in the Readme help.

Upgrading

Upgrading to this Version

Upgrade Complexity:

Easy ●

You may need to reset the toolbar to show new buttons added in GridView 9.3B if you are upgrading from an old version. Select View | Customize from the menu, then select each of the Toolbar's options and click the Reset button.

Note: When the GridView-RW add-on is active (i.e. GridView is started with the /RW parameter on the command line), the ChartView functions in GridView are not available.

Note: When upgrading other Adagio modules, if a new data dictionary is installed by the module, the GridView views originally created for earlier versions of the module should be adjusted to use the new dictionary. See the Release Notes for the modules to determine if there is a new dictionary. If there is a new dictionary, **Views used with GridView-RW MUST be updated to use the new dictionary to avoid the possibility of data corruption.** GridView has the ability to convert existing views when the dictionary changes with the release of an upgrade version of an Adagio module.

